

## Directions for Preparation and Use of Insecticides and Fungicides

The following formulae for the preparation and use of insecticides and fungicides are in accordance with the best practice. This calendar has been prepared exclusively for the fruit and truck growers of the Rogue River Valley; and, with this fact in view, only such matter is included as is thought necessary for the intelligent use of insecticides and fungicides in the control of such insect pests and fungous diseases as are of economic importance in the valley. For this reason, the treatment of such diseases as the Brown Rot of stone fruits, the various leaf spot diseases, the Bitter Rot of apples, etc., is omitted. Pear and apple scab, so serious in many sections, is of little economic importance in the Rogue River Valley. Only in some of the higher mountain valleys, where air drainage is insufficient, is scab found at all, and even there commercial varieties are rarely seriously attacked.

### BORDEAUX MIXTURE

This is the standard fall spray for apples and stone fruits. Bluestone (copper sulphate) 5 pounds Lime (unslacked) 5 pounds Water 50 gallons

Dissolve the bluestone by suspending it in a sack in water, and dilute to 25 gallons. Shake the lime to an even paste and add water to make 25 gallons. Mix these dilute solutions by pouring together slowly into the spray tank or barrel. Strain through a 20-mesh strainer made of brass wire while pouring into the spray tank. In large operations it is best to prepare stock solutions of both bluestone and lime. The bluestone may be dissolved at the rate of one pound per gallon of water. The lime may also be slaked, but not too far in advance of the time necessary to use it. By having a sufficient number of barrels for stock solutions, one man can easily keep three or four power spray outfits supplied with the Bordeaux mixture. An elevated platform upon which the mixing may be done will save a great deal of time. As little hand labor as possible should be the rule, and all that should be necessary in a well appointed mixing plant should be simply opening and closing valves or gates. A scale to weigh the materials used should be a necessary part of the equipment.

### RESIN-BORDEAUX MIXTURE

This is the standard spray for blackberries, raspberries and other cane fruits. Resin 1 pound Sal soda crystals  $\frac{1}{2}$  pound Water  $\frac{1}{2}$  gallon

Boil together until a clear brown color appears; then add the above to each 50 gallons of Bordeaux mixture made according to the 5-5-50 formula, given above. The reason for using the resin mixture is to cause the Bordeaux to spread and adhere better. The Resin-Bordeaux should be applied with a good spray pump and a nozzle giving a very fine mist spray. Keep the mixture well agitated, and before using remember that it should be carefully strained so as to keep out all materials which would tend to clog the nozzle.

### LIME-SULPHUR

This is the standard spray used during the spring for all fruit trees, vines, shrubs, etc., before the buds open. Lime-sulphur in concentrated form may be purchased, but there are many who prefer to boil their own solution. The proportions of lime, sulphur and water, according to the most recent investigations are:

Lime (unslacked) 1 pound Sulphur (flour or flowers) 2.2 pounds Water 1 gallon

In order to make 50 gallons of lime-sulphur at one time, all that is necessary to do is to multiply the above formula by 50. The formula will read:

Lime (unslacked) 50 pounds Sulphur (flour or flowers) 110 pounds Water 50 to 55 gallons total product when boiled

Put about 10 gallons of water in the kettle or boiler and start the fire. Place the lime in the kettle, and, after slaking has well started, add the dry sulphur and mix it thoroughly, adding water enough to maintain a thin paste. Sift the sulphur so that there will be no lumps. After the slaking and mixing are completed, add water to about 50 gallons on the measuring stick or to a mark on the side of the boiler, and boil, stirring until the sulphuric scum disappears. Then add water to about the height of 50 gallons and boil down to about 55 gallons if the spray is to be used at once. If it is desired to keep it for a short while, it may be boiled down to 50 gallons. During the boiling process the mixture should be well stirred. As a rule, 60 minutes of vigorous boiling will cause the sulphur to unite completely with the lime. A slow fire will necessarily take longer. Do not overboil; when the sulphur has combined with the lime and the mixture is to be applied at once, continued boiling only adds expense and does not help or benefit the spray. Properly made lime-sulphur is an amber-colored liquid, and there should be very little sediment. After settling and cooling the mixture should be tested with a hydrometer. The following table, which may be used for the commercial as well as the home-boiled lime-sulphur, indicates the proper dilution for the various concentrations:

Table for Diluting Concentrated Lime-Sulphur Solutions.

Reading of Hydrometer	Specific Gravity	Number of gals. water to one gal. lime-sulphur solution. For dormant spraying.	Amount of dilution
40	1.357	1 gal. lime-sulphur	11.0 gals. water
39	1.345	1 gal. lime-sulphur	10.5 gals. water
38	1.333	1 gal. lime-sulphur	10.1 gals. water
37	1.322	1 gal. lime-sulphur	9.7 gals. water
36	1.310	1 gal. lime-sulphur	9.3 gals. water
35	1.298	1 gal. lime-sulphur	9.0 gals. water
34	1.288	1 gal. lime-sulphur	8.6 gals. water
33	1.277	1 gal. lime-sulphur	8.2 gals. water
32	1.267	1 gal. lime-sulphur	7.9 gals. water
31	1.256	1 gal. lime-sulphur	7.5 gals. water
30	1.246	1 gal. lime-sulphur	7.2 gals. water
29	1.236	1 gal. lime-sulphur	6.9 gals. water
28	1.226	1 gal. lime-sulphur	6.5 gals. water
27	1.216	1 gal. lime-sulphur	6.2 gals. water
26	1.206	1 gal. lime-sulphur	5.9 gals. water
25	1.197	1 gal. lime-sulphur	5.6 gals. water
24	1.188	1 gal. lime-sulphur	5.3 gals. water
23	1.178	1 gal. lime-sulphur	4.9 gals. water
22	1.169	1 gal. lime-sulphur	4.6 gals. water
21	1.160	1 gal. lime-sulphur	4.3 gals. water
20	1.152	1 gal. lime-sulphur	4.1 gals. water

This table is constructed for a dilution of 4.5 degrees Beams or its equivalent 1.039 specific gravity.

Tables Comparing Beaume's Hydrometer and Specific Gravities.

Degrees Beaume	Specific Gravity	Degrees Beaume	Specific Gravity	Degrees Beaume	Specific Gravity
40	1.357	14	1.101	27	1.216
39	1.345	15	1.099	28	1.226
38	1.333	16	1.118	29	1.236
37	1.322	17	1.126	30	1.246
36	1.310	18	1.134	31	1.256
35	1.298	19	1.143	32	1.267
34	1.288	20	1.152	33	1.277
33	1.277	21	1.160	34	1.288
32	1.267	22	1.169	35	1.299
31	1.256	23	1.178	36	1.310
30	1.246	24	1.188	37	1.322
29	1.236	25	1.197	38	1.333
28	1.226	26	1.206	39	1.345
27	1.216	40	1.357		

Rules for Determining Number of Dilutions and Density of Spray.

If the density of the commercial solution or the home-made wash has been first determined by the use of a hydrometer, sprays of any desired density may be calculated by using chemical analyses. The rule for obtaining the number of dilutions is as follows: Divide the decimal of the concentrate by the decimal of the spray desired, the quotient will be the number of dilutions. Example: The concentrated lime-sulphur solution tests 34 degrees Beaume which in the table is 1.288 specific gravity. It is desired to use the lime-sulphur solution to spray upon trees at 3 degrees Beaume which is 1.020 specific gravity. The decimal of the concentrate is .288 which divided by .020 equals 14.4, which is the number of dilutions required, and which, of course, is obtained by adding 13.4 volumes of water to one volume of the concentrated lime-sulphur solution. This rule is based upon the general fact that the density of a solution heavier than water varies inversely with the number of dilutions. Another example: Supposing the decimal of the concentrate is known and this concentrate is diluted by a certain number of volumes of water, what is the decimal of the spray? Let us take the figures in the example above. The decimal of the concentrate is .288 and 13.4 volumes of water are added to it. 13.4 plus 1 equals the number of dilutions, .288 divided by 14.4 equals .020 which is the decimal of the spray and corresponds to 3 degrees Beaume.

### SELF-BOILED LIME-SULPHUR

This is the standard summer spray for peaches and other stone fruits to prevent the fruit spot disease. Its use, however, is never necessary if proper fall spraying with Bordeaux has been done. This spray is much safer than dilute lime-sulphur solutions, as it will not injure foliage. It may be used to prevent apple and pear scab where this disease appears. It also has a beneficial effect in a limited way in the control of scale. Infestation of the fruit may be checked by its use.

Lime (unslacked) 8 pounds Sulphur (flour or flowers) 8 pounds Water 56 gallons

The lime should be placed in a barrel and enough water poured on to almost cover it. As soon as the lime begins to slack, the sulphur should be added after sifting it so as to break the lumps. The mixture should be stirred and more water added as need to form a thick paste at first and then gradually a thin paste. The heat of the slackening lime will cook the mixture and from 5 to 15 minutes will be necessary, according to the quickness of the lime. Be sure not to let it overcook as this would tend to form compounds which would burn. As soon as the sulphur and lime have reached the paste state, fill up the barrel to 50 gallons with cold water. Do not use hot water in making this mixture. For large operations, proportionate amounts of lime and sulphur should be used, and it will be found that it is easier to make large quantities than small amounts.

### ATOMIC SULPHUR

Atomic sulphur has become the standard spray for mildew of apples, roses, grapes, etc. It is also a good apple and pear scab preventive. In the calendar it has replaced the iron sulphide spray, and may also be used wherever self-boiled lime-sulphur is advised. Use at the rate of 7 pounds to 50 gallons of water.

Boil together until a clear brown color appears; then add the above to each 50 gallons of Bordeaux mixture made according to the 5-5-50 formula, given above. The reason for using the resin mixture is to cause the Bordeaux to spread and adhere better. The Resin-Bordeaux should be applied with a good spray pump and a nozzle giving a very fine mist spray. Keep the mixture well agitated, and before using remember that it should be carefully strained so as to keep out all materials which would tend to clog the nozzle.

### NITRATE OF SODA SPRAY

This spray is to be used as a stimulant which will have the effect of inducing shy bearing trees to set fruit. Many varieties of fruits, although blooming heavily, will shed their blossoms or even the fruits after they reach considerable size. This is due to sterility of the blossoms. The nitrate of soda spray, if applied a month or six weeks before blossoming, will act as a stimulant and tend to make the blossoms set fruit. The spray will also cause the trees to bloom a week or ten days earlier than normal. In spraying, this should be taken into consideration on account of the earlier exposure of the blossoms to frost conditions. The nitrate of soda may be combined with lime-sulphur solution in the spring spraying; however, where eggs of aphides are present, the lime-sulphur spray should be delayed until the buds are beginning to swell. In this case, the nitrate of soda would have to be put on earlier and independent of the lime-sulphur. For pears, the lime-sulphur solution and the nitrate of soda may always be combined, providing it is remembered that the early spraying will tend to advance the blooming period. In combining nitrate of soda with lime-sulphur solution, caustic soda is omitted. Three formulas are given:

(Ballard's Formulae.)

Double Strength—To Be Used on Very Shy Bearers.

Nitrate of soda 200 pounds Caustic soda 25 pounds Water 200 gallons

Normal Strength.

Nitrate of soda 100 pounds Caustic soda 10 pounds Water 200 gallons

Nitrate of Soda and Lime-sulphur Solution Combined.

Nitrate of soda 200 pounds Lime-sulphur (diluted) 200 pounds

In making up the nitrate of soda spray, the nitrate of soda, as well as the caustic soda, should first be dissolved in water, in which the same way as bluestone is dissolved. In making up the nitrate of soda—lime-sulphur spray, the diluted lime-sulphur should be considered the same as water in the other formulas.

### DISTILLATE-OIL EMULSION

This is the standard spray for thrips.

Water 6 gallons Lye (98 per cent) 2 pounds Fish oil 1½ gallons

Put water in boiler and add lye. When dissolved and the water boiling, pour in fish oil, and boil for two hours. When soap has boiled sufficiently it should have aropy effect when stirred. This formula gives about 40 pounds of moderately firm soap.

The distillate-oil stock emulsion should be made as follows:

Hot water 12 gallons Fish-oil whale-oil soap (above formula) 30 pounds Distillate-oil (raw) 30 to 34 degrees Beaume 20 gallons

Have the water boiling when put into the spray tank and add soap while agitator is running at good speed. When soap is thoroughly dissolved, pour in the distillate-oil slowly, well mixed, pump out through the spray nozzle at a pressure of not less than 175 pounds into a storage tank. This is the stock emulsion and contains 55 percent oil. To make a 3 per cent emulsion use  $\frac{1}{5}$  gals. of this stock in each 100 gallon tank. To dilute, first put the stock emulsion in spray tank and then add water, keeping agitator running. To make the spray more effective, tobacco black leaf or sulphate of nicotine may be added after the emulsion has been diluted. The amount of each to add will be in accordance with the formula given elsewhere.

### WHALE-OIL SOAP AND QUASSIA

Whale-oil soap 10 pounds Quassia 5 pounds Water 100 gallons

Place the quassia chips in a sack, cover with about 10 gallons of water and soak for 24 hours. Then boil, remove the chips, add the soap and boil until dissolved. Add water to make 100 gallons. For making whale-oil soap see formula given elsewhere. This formula has given good success in destroying soft bodied insects like plant lice, young squash bugs, etc.

### ARSENATE OF LEAD

Arsenate of lead 4 pounds Water 100 gallons

It is better to purchase arsenate of lead than to attempt to make it. In mixing, preparatory to spraying, the amount of arsenate of lead for each spray tank full should be worked into a very thin paste having the appearance of milk of lime. It should never be thrown as a mass into the spray tank. This is the standard spray for codling moth and other eating insects.

### TOBACCO SPRAYS

(1)

Tobacco black leaf 1 gallon Water 65 gallons

(2)

Sulphate of nicotine (Black-Leaf 40) 1 pint Water 100 to 125 gallons

This is the standard summer spray for sucking insects, such as green aphids, woolly aphids and other aphides, such as tobacco hornworms, etc.

### HELLEBORE

Hellebore 1 ounce Water 2 gallons

This is valuable as an insecticide for use on vegetables which are almost ready for market and on which arsenicals cannot be used.

### PYRETHRUM

Pyrethrum 1 ounce Water 2 gallons